

BIOT-SAVART LAW: FORCE ON OTHER CURRENTS

Link to: [physicspages home page](#).

To leave a comment or report an error, please use the auxiliary blog.

Reference: Griffiths, David J. (2007) Introduction to Electrodynamics, 3rd Edition; Prentice Hall - Problem 5.10.

Here are a couple more examples of calculating the magnetic field due to a steady current in a wire.

Suppose we have an infinite straight wire on the x axis carrying a current I in the $+x$ direction. A square loop of side length a (also carrying current I flowing clockwise around the square as viewed from above) is placed in the xy plane so that the side nearest the wire is parallel to the wire and along the line $y = -s$. What is the force on the loop due to the wire?

First, we need to work out the magnetic field caused by the current in the wire. We can apply the result we used earlier in calculating the magnetic field due to a wire segment. In this case, we get, for a wire a perpendicular distance d from the observation point \mathbf{r} :

$$\mathbf{B}_1(\mathbf{r}) = \hat{\mathbf{z}} \frac{I\mu_0}{4\pi} \int \frac{|\mathbf{r} - \mathbf{r}'| \sin \theta}{|\mathbf{r} - \mathbf{r}'|^3} dl' \quad (1)$$

$$= \hat{\mathbf{z}} \frac{I\mu_0}{4\pi} \int_{-\infty}^{\infty} \frac{d}{(d^2 + x^2)^{3/2}} dx \quad (2)$$

$$= \hat{\mathbf{z}} \frac{I\mu_0}{2\pi d} \quad (3)$$

The magnetic field points in the $+z$ direction above the x axis (that is, where $y > 0$) and in the $-z$ direction on the other side of the x axis. Since the loop is on the lower side of the x axis and the current flows clockwise as seen from above, \mathbf{I} is in the $+x$ direction on the side of the loop nearest the wire and in the $-x$ direction on the side farthest from the wire. From the symmetry of the problem the forces on the two sides of the square that are perpendicular to the wire cancel, so we need to work out only the forces on the two edges parallel to the wire. We get, using the form of the Lorentz force law for linear currents

$$\mathbf{F} = \int \mathbf{I} \times \mathbf{B} dl \quad (4)$$

$$= \frac{aI^2\mu_0}{2\pi} \left(\frac{1}{s} - \frac{1}{s+a} \right) \hat{\mathbf{y}} \quad (5)$$

Now suppose we have an equilateral triangle (side length a) with its base aligned with the wire, and along the line $y = -s$. As before, the current flows clockwise around the triangle.

The force on the edge nearest the wire is the same as for the square, namely

$$\mathbf{F}_1 = -\frac{aI^2\mu_0}{2\pi s} \hat{\mathbf{y}} \quad (6)$$

To calculate the force on one of the other edges, we can take the coordinates of the vertex on this edge nearest the wire to be $(0, -s)$. Then the equation of the line of which that edge is a part is

$$y = -x \tan \frac{\pi}{3} - s \quad (7)$$

$$= -\sqrt{3}x - s \quad (8)$$

The line increment along this edge is

$$dl = \sqrt{dx^2 + dy^2} \quad (9)$$

$$= 2dx \quad (10)$$

The integral we need to do to figure out the force on this one edge is

$$F_2 = \frac{I^2\mu_0}{2\pi} \int \frac{dl}{d} \quad (11)$$

where d is the perpendicular distance from a point on the edge of the triangle to the infinite wire. In our coordinates, $d = |y|$ and over the extent of this edge x varies from 0 to $\frac{a}{2}$ so we get

$$F_2 = \frac{I^2\mu_0}{2\pi} \int_0^{\frac{a}{2}} \frac{2dx}{\sqrt{3}x + s} \quad (12)$$

$$= \frac{I^2\mu_0}{\sqrt{3}\pi} \ln \left(1 + \frac{\sqrt{3}a}{2s} \right) \quad (13)$$

This is the *total* force on the edge, which from the cross product right hand rule is perpendicular to the edge and pointing towards the interior of the triangle. The force on the third edge will, by symmetry, point in a direction that is the mirror image of F_2 (reflected about the line $x = a/2$). Thus the components of these two forces parallel to the wire cancel, and the net force from these two edges is twice the perpendicular component of F_2 . Since F_2 is perpendicular to the edge of the triangle, which in turn makes an angle of $\pi/3$ with the x axis, F_2 makes an angle of $\pi/6$ with the x axis (draw a little diagram if this isn't clear), so its perpendicular component is $F_2 \sin \frac{\pi}{6} = \frac{F_2}{2}$ and the total perpendicular component from the two edges of the triangle is $2 \times \frac{F_2}{2} = F_2$. This component is directed in the $+y$ direction while the force on the bottom edge is in the $-y$ direction, so the net force is

$$\mathbf{F} = \left[\frac{I^2 \mu_0}{\sqrt{3} \pi} \ln \left(1 + \frac{\sqrt{3}a}{2s} \right) - \frac{aI^2 \mu_0}{2\pi s} \right] \hat{\mathbf{y}} \quad (14)$$

$$= \frac{I^2 \mu_0}{2\pi} \left[\frac{2}{\sqrt{3}} \ln \left(1 + \frac{\sqrt{3}a}{2s} \right) - \frac{a}{s} \right] \hat{\mathbf{y}} \quad (15)$$

PINGBACKS

Pingback: [Magnetic field of a solenoid](#)

Pingback: [Ampère's law for steady currents](#)

Pingback: [Electron speed in a copper wire](#)

Pingback: [Magnetic vector potential of an infinite wire](#)

Pingback: [Currents and relativity](#)

Pingback: [Magnetic vector potential from magnetic field](#)

Pingback: [Emf near an infinite wire](#)