

## WAVE EQUATION: SINUSOIDAL WAVES AND COMPLEX NOTATION

Link to: [physicspages home page](#).

To leave a comment or report an error, please use the [auxiliary blog](#).

References: Griffiths, David J. (2007), Introduction to Electrodynamics, 3rd Edition; Pearson Education - Problem 9.3.

Any function of form  $f = f(z \pm vt)$  (for a constant  $v$ ) is a solution of the wave equation

$$(0.1) \quad \frac{\partial^2 f}{\partial z^2} = \frac{1}{v^2} \frac{\partial^2 f}{\partial t^2}$$

Probably the most commonly used solution is the sine wave, which can be written as either a sine or a cosine, either of which gives the most general sinusoidal solution. For example, we can write

$$(0.2) \quad f(z, t) = A \cos(k(z - vt) + \delta)$$

where  $k$ ,  $v$  and  $\delta$  are constants. The wavelength  $\lambda$  is the distance (at constant time) between two successive peaks, which occurs when  $z$  advances far enough to increase the argument of the cosine by  $2\pi$ . Therefore

$$(0.3) \quad k\lambda = 2\pi$$

$$(0.4) \quad \lambda = \frac{2\pi}{k}$$

The parameter  $k$  is called the *wave number*.

As we saw earlier,  $v$  is the speed of the wave. The parameter  $\delta$  is the phase of the wave, and allows for waves that don't have their maximum at  $z - vt = 0$ . Suppose that at  $t = 0$  the maximum of the wave that is closest to  $z = 0$  is at  $z = z_m$ . Then the argument of the cosine must be zero at that point, so

$$(0.5) \quad kz_m = -\delta$$

$$(0.6) \quad z_m = -\frac{\delta}{k}$$

Thus a positive phase ( $\delta > 0$ ) means that the peak of the wave lags behind  $z = 0$ , while a negative phase ( $\delta < 0$ ) means the peak leads  $z = 0$ .

It's more common to write the wave in terms of  $k$  and the angular frequency, defined as

$$(0.7) \quad \omega \equiv kv = \frac{2\pi v}{\lambda}$$

so we get

$$(0.8) \quad f(z, t) = A \cos(kz - \omega t + \delta)$$

It turns out that it's often more convenient to represent a sinusoidal wave as the real part of a complex exponential. That is

$$(0.9) \quad f(z, t) = \Re \left( A e^{i(kz - \omega t + \delta)} \right)$$

We can then define a complex wave function

$$(0.10) \quad \tilde{f}(z, t) \equiv \tilde{A} e^{i(kz - \omega t)}$$

$$(0.11) \quad \tilde{A} \equiv A e^{i\delta}$$

Physical waves are, of course, always real functions (well, except in quantum mechanics, where complex wave functions are the norm, but even there, any physical interpretation of the quantum wave function requires extracting a real value from the complex function).

Working with complex exponentials is, in most cases, easier than working with sines and cosines, although the formulas aren't quite trivial. For example, if we want to add two waves  $f_1$  and  $f_2$  then we get

$$(0.12) \quad f_3 = f_1 + f_2$$

$$(0.13) \quad = \Re(\tilde{f}_1 + \tilde{f}_2)$$

If the two waves to be added have the same  $k$  and  $\omega$ , then we need to find the new amplitude  $A_3$  and phase  $\delta_3$  in terms of the amplitudes and phases of the constituent waves. That is

$$(0.14) \quad \tilde{f}_3 = \tilde{A}_3 e^{i(kz - \omega t)}$$

$$(0.15) \quad A_3 e^{i\delta_3} e^{i(kz - \omega t)} = (\tilde{A}_1 + \tilde{A}_2) e^{i(kz - \omega t)}$$

$$(0.16) \quad A_3 e^{i\delta_3} = A_1 e^{i\delta_1} + A_2 e^{i\delta_2}$$

Taking the square modulus of both sides, we get

$$(0.17) \quad A_3^2 = A_1^2 + A_2^2 + A_1 A_2 \left( e^{i(\delta_1 - \delta_2)} + e^{-i(\delta_1 - \delta_2)} \right)$$

$$(0.18) \quad = A_1^2 + A_2^2 + 2A_1 A_2 \cos(\delta_1 - \delta_2)$$

$$(0.19) \quad A_3 = \sqrt{A_1^2 + A_2^2 + 2A_1 A_2 \cos(\delta_1 - \delta_2)}$$

To get the phase, we can use

$$(0.20) \quad \tilde{A}_3 = A_3 (\cos \delta_3 + i \sin \delta_3)$$

$$(0.21) \quad \tan \delta_3 = \frac{\Im \tilde{A}_3}{\Re \tilde{A}_3}$$

$$(0.22) \quad = \frac{\Im (\tilde{A}_1 + \tilde{A}_2)}{\Re (\tilde{A}_1 + \tilde{A}_2)}$$

$$(0.23) \quad = \frac{A_1 \sin \delta_1 + A_2 \sin \delta_2}{A_1 \cos \delta_1 + A_2 \cos \delta_2}$$

$$(0.24) \quad \delta_3 = \arctan \left[ \frac{A_1 \sin \delta_1 + A_2 \sin \delta_2}{A_1 \cos \delta_1 + A_2 \cos \delta_2} \right]$$

Keep in mind that these formulas work only for adding two waves with the *same* wave number  $k$  and frequency  $\omega$ .

#### PINGBACKS

Pingback: Waves: boundary condition with a massive knot

Pingback: Waves: polarization

Pingback: Electromagnetic waves in vacuum